

Setting up Sharp MX MFPs to scan to network folder (SMB)


For older web-style interface MFPs

MX-M350, MX-M450, MX-M550, MX-M620, MX-M700


## Configuring The MX Monochrome Imager For Scanning To Network Folder

Log in to the Sharp Imager's web interface home page by typing the IP address of your imager using a web browser such as Internet Explorer.

**Note:** The IP address shown below is only an example. Yours may be different.



### Adding A Network Folder On An MX Monochrome Imager




#### Setting Up A Network Folder On An MX Color Imager

- 1. Enter the Address Name. Note: This will be the display name
- 2. Enter the Folder Path (IP address or Computer Name) of the computer where the Network Folder resides and Directory. Example: \\ipaddress\folder

Note: This is case sensitive


- 3. User Name: This must be a Windows Local User (NOT Group). Be sure to give it full Security and Sharing rights.
- 4. Password: Enter the password assigned to the user. This is case sensitive

NOTE: To add a Windows User and setup a Windows Network Folder, see the next pages.




### **Creating A Windows User Account**

Step 1. Go to the Control Panel > Double-Click User Accounts



## **Creating A Windows User Account**


Step 4. Right-Click Users > Select New User...




### Promoting A Windows User Account To Administrator

Step 6. Click Groups

Step 7. Double-click Administrators




### Sharing A Windows Folder And Assigning Permissions



# Assigning An User Full Permissions

6. Select the newly added user, select "Full Control" and click OK



# Assigning An User Full Security Rights

9. Type the name of the "local" user and click the Check Name button

